



REPUTE 3 FAQ

HOW TO INSTALL A REPUTE 3 SL WAN LICENCE

A Repute 3 SL WAN licence is stored in a secure location on your server.

1. Make sure you have the Thales Sentinel run-time environment installed on your server. You can obtain the setup program for the runtime here:

www.geocentrix.co.uk/support/drivers.html

2. Open your web browser, type localhost:1947 into the address bar, and press ENTER. The Sentinel Admin Control Centre (ACC) will open.
3. On the **Sentinel Keys** tab, find the entry for **Vendor** 48297 with the **Key Type** Reserved for New SL Key. (If this is missing, please contact Geocentrix Technical Support for advice.)

Location	Vendor	Key ID	Key Type	Configuration	Version	Sessions	Actions
Local	48297 (48297)		Reserved for New SL Key	SL	9.13		Fingerprint

4. Under the column heading **Actions**, click on the button labelled **Fingerprint**, choose where to save the fingerprint, and press **Save**. The Control Centre will generate a fingerprint for your computer and save it with the name fingerprint@<Company>.c2v, replacing "<Company>" with your company name (e.g. fingerprint@Geocentrix.c2v).
 5. Send that c2v file via email to support@geocentrix.co.uk, with the subject 'Fingerprint to activate Repute 3 licence'.
 6. Close the Admin Control Centre and wait for Geocentrix to respond via email.
-
7. When we reply, we will send you three files as follows (x = 0-9 or a-e, XXX = Std/Pro/Ent)):

```

<Company/>@<Host/> - activation.v2c ❶
<Company>@<PIN>@<Host/> - Repute key.v2c ❷
RPT-0300-xxxx-xxxx-xxxx-XXX.lic ❸

```

where <Company/> is your company's name, <PIN/> is the id of your soft licence, and <Host/> is the host name of your computer.

8. Save these files in a temporary folder on your computer and then reopen Repute.
9. On the **Licence** tab, click the button labelled **Import V2C File** Navigate to your chosen temporary folder, select the activation file ❶ above, and press **Open**.
10. Repeat Step 9 for the Repute key file ❷.

IMPORTANT! The v2c files must be applied in the order given, otherwise this will not work

11. You can delete files ❶ and ❷ since they can only be used once.
12. Finally, register Repute on every client machine where you want it to be used, following these instructions, remembering to enter the hostname of you server when you do so:

www.geocentrix.co.uk/repute/downloads/3.0/How to register a Repute 3 licence.pdf

For further help, please contact Geocentrix Support quoting your company name and licence no.