



REPUTE FAQ

HOW TO PERFORM A SILENT INSTALLATION OF REPUTE

The information given here is needed should you want to automatically configure Client Workstations to run Repute.

Program files

The Repute executable (Repute25.exe), associated libraries (DLLs and BPLs), and other files are installed in one of the following folders:

- 64-bit Windows: C:\Program Files (x86)\Geocentrix\Repute\2.5
- 32-bit Windows: C:\Program Files\Geocentrix\Repute\2.5

Configuration files

Repute's configuration files are installed in one of the following folders:

- Windows Vista and later: C:\ProgramData\Geocentrix\Repute\2.5
- Windows XP: C:\Documents and Settings\All Users\Application Data\Geocentrix\Repute\2.5

IMPORTANT: The user should have full read/write permissions to the appropriate folder above

The following configuration files are used in the normal operation of the program:

- Repute2.lic (licence file, in XML format)
- Repute2.cfg (configuration file, in XML format)

Do NOT edit these files except as instructed by Geocentrix Technical Support.

Shared documents

Repute's Tutorials and other shared documents are installed in one of the following folders:

- Windows Vista and later: C:\Users\Public\Documents\Geocentrix\Repute\2.5
- Windows XP: C:\Documents and Settings\All Users\Documents\Geocentrix\Repute\2.5

Command line flags for the setup program

To install Repute silently, enter the following command via a command line window:

```
Repute25Setup.exe /s /l=<logfile.txt>
```

where <logfile.txt> is the name you want to give to the log file created by the process. To uninstall Repute silently, enter the following command:

```
Repute25Setup.exe MODIFY=FALSE REMOVE=TRUE UNINSTALL=YES
```

For further information, please contact Geocentrix Technical Support at the email address below.