



REPUTE 3 FAQ

HOW TO PERFORM A SILENT INSTALLATION OF REPUTE 3

This FAQ gives information needed to automatically configure Client Workstations to run Repute 3 on Microsoft Windows 10 or 11.

COMMAND LINE FLAGS FOR THE SETUP PROGRAM

To install Repute silently, enter the following command via a command line window:

```
Repute3Setup.exe /noui
```

To install Repute silently with a log "Repute3Setup.log" in the same folder as the setup program:

```
Repute3Setup.exe /noui /exelog
```

To install Repute silently with a log "Repute3Install.log" in the pre-existing folder "C:\Temp":

```
Repute3Setup.exe /noui /exelog "C:\Temp\Repute3Install.log"
```

To uninstall Repute silently with a log "Repute3Uninstall.log" in the pre-existing folder "C:\Temp":

```
Repute3Setup.exe /x /exelog "Repute3Uninstall.log"
```

INSTALLATION FOLDERS

The Repute 3 setup program (Repute3Setup.exe) installs executables, libraries (DLLs and BPLs), project files (RPTZ files), and other supporting files in the following folders:

- **Program files:** C:\Program Files\Geocentrix\Repute\3.0
- **Common program files:** C:\Program Files (x86)\Common Files\Geocentrix
- **Licence files:** C:\ProgramData\Geocentrix\Repute\3.0
- **Shared documents:** C:\Users\Public\Documents\Geocentrix\Repute\3.0
- **Configuration files:** C:\Users\<Username>\AppData\Roaming\Geocentrix\Repute\3.0

For further help, please contact Geocentrix Support quoting your company name and licence no.